

NAME

e2fsck – check a Linux ext2/ext3/ext4 file system

SYNOPSIS

e2fsck [**-pacnyrdfkvtDFV**] [**-b** *superblock*] [**-B** *blocksize*] [**-l|-L** *bad_blocks_file*] [**-C** *fd*] [**-j** *external-journal*] [**-E** *extended_options*] [**-z** *undo_file*] *device*

DESCRIPTION

e2fsck is used to check the ext2/ext3/ext4 family of file systems. For ext3 and ext4 filesystems that use a journal, if the system has been shut down uncleanly without any errors, normally, after replaying the committed transactions in the journal, the file system should be marked as clean. Hence, for filesystems that use journalling, **e2fsck** will normally replay the journal and exit, unless its superblock indicates that further checking is required.

device is a block device (e.g., */dev/sdc1*) or file containing the file system.

Note that in general it is not safe to run **e2fsck** on mounted filesystems. The only exception is if the **-n** option is specified, and **-c**, **-l**, or **-L** options are *not* specified. However, even if it is safe to do so, the results printed by **e2fsck** are not valid if the filesystem is mounted. If **e2fsck** asks whether or not you should check a filesystem which is mounted, the only correct answer is “no”. Only experts who really know what they are doing should consider answering this question in any other way.

If **e2fsck** is run in interactive mode (meaning that none of **-y**, **-n**, or **-p** are specified), the program will ask the user to fix each problem found in the filesystem. A response of 'y' will fix the error; 'n' will leave the error unfixed; and 'a' will fix the problem and all subsequent problems; pressing Enter will proceed with the default response, which is printed before the question mark. Pressing Control-C terminates **e2fsck** immediately.

OPTIONS

-a This option does the same thing as the **-p** option. It is provided for backwards compatibility only; it is suggested that people use **-p** option whenever possible.

-b *superblock*

Instead of using the normal superblock, use an alternative superblock specified by *superblock*. This option is normally used when the primary superblock has been corrupted. The location of backup superblocks is dependent on the filesystem's blocksize, the number of blocks per group, and features such as **sparse_super**.

Additional backup superblocks can be determined by using the **mke2fs** program using the **-n** option to print out where the superblocks exist, supposing **mke2fs** is supplied with arguments that are consistent with the filesystem's layout (e.g. blocksize, blocks per group, **sparse_super**, etc.).

If an alternative superblock is specified and the filesystem is not opened read-only, **e2fsck** will make sure that the primary superblock is updated appropriately upon completion of the filesystem check.

-B *blocksize*

Normally, **e2fsck** will search for the superblock at various different block sizes in an attempt to find the appropriate block size. This search can be fooled in some cases. This option forces **e2fsck** to only try locating the superblock at a particular blocksize. If the superblock is not found, **e2fsck** will terminate with a fatal error.

-c This option causes **e2fsck** to use **badblocks(8)** program to do a read-only scan of the device in order to find any bad blocks. If any bad blocks are found, they are added to the bad block inode to prevent them from being allocated to a file or directory. If this option is specified twice, then the bad block scan will be done using a non-destructive read-write test.

-C *fd* This option causes **e2fsck** to write completion information to the specified file descriptor so that the progress of the filesystem check can be monitored. This option is typically used by programs which are running **e2fsck**. If the file descriptor number is negative, then absolute value of the file descriptor will be used, and the progress information will be suppressed initially. It can later be enabled by sending the **e2fsck** process a SIGUSR1 signal. If the file descriptor specified is 0,

e2fsck will print a completion bar as it goes about its business. This requires that **e2fsck** is running on a video console or terminal.

- d** Print debugging output (useless unless you are debugging **e2fsck**).
- D** Optimize directories in filesystem. This option causes **e2fsck** to try to optimize all directories, either by reindexing them if the filesystem supports directory indexing, or by sorting and compressing directories for smaller directories, or for filesystems using traditional linear directories.

Even without the **-D** option, **e2fsck** may sometimes optimize a few directories --- for example, if directory indexing is enabled and a directory is not indexed and would benefit from being indexed, or if the index structures are corrupted and need to be rebuilt. The **-D** option forces all directories in the filesystem to be optimized. This can sometimes make them a little smaller and slightly faster to search, but in practice, you should rarely need to use this option.

The **-D** option will detect directory entries with duplicate names in a single directory, which **e2fsck** normally does not enforce for performance reasons.

-E *extended_options*

Set **e2fsck** extended options. Extended options are comma separated, and may take an argument using the equals ('=') sign. The following options are supported:

ea_ver=extended_attribute_version

Set the version of the extended attribute blocks which **e2fsck** will require while checking the filesystem. The version number may be 1 or 2. The default extended attribute version format is 2.

journal_only

Only replay the journal if required, but do not perform any further checks or repairs.

fragcheck

During pass 1, print a detailed report of any discontinuous blocks for files in the filesystem.

discard

Attempt to discard free blocks and unused inode blocks after the full filesystem check (discarding blocks is useful on solid state devices and sparse / thin-provisioned storage). Note that discard is done in pass 5 AFTER the filesystem has been fully checked and only if it does not contain recognizable errors. However there might be cases where **e2fsck** does not fully recognize a problem and hence in this case this option may prevent you from further manual data recovery.

nodiscard

Do not attempt to discard free blocks and unused inode blocks. This option is exactly the opposite of discard option. This is set as default.

no_optimize_extents

Do not offer to optimize the extent tree by eliminating unnecessary width or depth. This can also be enabled in the options section of **/etc/e2fsck.conf**.

optimize_extents

Offer to optimize the extent tree by eliminating unnecessary width or depth. This is the default unless otherwise specified in **/etc/e2fsck.conf**.

inode_count_fullmap

Trade off using memory for speed when checking a file system with a large number of hard-linked files. The amount of memory required is proportional to the number of inodes in the file system. For large file systems, this can be gigabytes of memory. (For example, a 40TB file system with 2.8 billion inodes will consume an additional 5.7 GB memory if this optimization is

enabled.) This optimization can also be enabled in the options section of `/etc/e2fsck.conf`.

no_inode_count_fullmap

Disable the `inode_count_fullmap` optimization. This is the default unless otherwise specified in `/etc/e2fsck.conf`.

readahead_kb

Use this many KiB of memory to pre-fetch metadata in the hopes of reducing `e2fsck` runtime. By default, this is set to the size of two block groups' inode tables (typically 4MiB on a regular ext4 filesystem); if this amount is more than 1/50th of total physical memory, `readahead` is disabled. Set this to zero to disable `readahead` entirely.

bmap2extent

Convert block-mapped files to extent-mapped files.

fixes_only

Only fix damaged metadata; do not optimize htree directories or compress extent trees. This option is incompatible with the `-D` and `-E bmap2extent` options.

unshare_blocks

If the filesystem has shared blocks, with the shared blocks read-only feature enabled, then this will unshare all shared blocks and unset the read-only feature bit. If there is not enough free space then the operation will fail. If the filesystem does not have the read-only feature bit, but has shared blocks anyway, then this option will have no effect. Note when using this option, if there is no free space to clone blocks, there is no prompt to delete files and instead the operation will fail.

Note that `unshare_blocks` implies the `-f` option to ensure that all passes are run. Additionally, if `-n` is also specified, `e2fsck` will simulate trying to allocate enough space to deduplicate. If this fails, the exit code will be non-zero.

- f** Force checking even if the file system seems clean.
- F** Flush the filesystem device's buffer caches before beginning. Only really useful for doing `e2fsck` time trials.
- j *external-journal***
Set the pathname where the external-journal for this filesystem can be found.
- k** When combined with the `-c` option, any existing bad blocks in the bad blocks list are preserved, and any new bad blocks found by running `badblocks(8)` will be added to the existing bad blocks list.
- l *filename***
Add the block numbers listed in the file specified by *filename* to the list of bad blocks. The format of this file is the same as the one generated by the `badblocks(8)` program. Note that the block numbers are based on the blocksize of the filesystem. Hence, `badblocks(8)` must be given the blocksize of the filesystem in order to obtain correct results. As a result, it is much simpler and safer to use the `-c` option to `e2fsck`, since it will assure that the correct parameters are passed to the `badblocks` program.
- L *filename***
Set the bad blocks list to be the list of blocks specified by *filename*. (This option is the same as the `-l` option, except the bad blocks list is cleared before the blocks listed in the file are added to the bad blocks list.)

- n** Open the filesystem read-only, and assume an answer of 'no' to all questions. Allows **e2fsck** to be used non-interactively. This option may not be specified at the same time as the **-p** or **-y** options.
- p** Automatically repair ("preen") the file system. This option will cause **e2fsck** to automatically fix any filesystem problems that can be safely fixed without human intervention. If **e2fsck** discovers a problem which may require the system administrator to take additional corrective action, **e2fsck** will print a description of the problem and then exit with the value 4 logically or'ed into the exit code. (See the **EXIT CODE** section.) This option is normally used by the system's boot scripts. It may not be specified at the same time as the **-n** or **-y** options.
- r** This option does nothing at all; it is provided only for backwards compatibility.
- t** Print timing statistics for **e2fsck**. If this option is used twice, additional timing statistics are printed on a pass by pass basis.
- v** Verbose mode.
- V** Print version information and exit.
- y** Assume an answer of 'yes' to all questions; allows **e2fsck** to be used non-interactively. This option may not be specified at the same time as the **-n** or **-p** options.
- z** *undo_file*
Before overwriting a file system block, write the old contents of the block to an undo file. This undo file can be used with [e2undo\(8\)](#) to restore the old contents of the file system should something go wrong. If the empty string is passed as the *undo_file* argument, the undo file will be written to a file named `e2fsck-device.e2undo` in the directory specified via the `E2FSPROGS_UNDO_DIR` environment variable.

WARNING: The undo file cannot be used to recover from a power or system crash.

EXIT CODE

The exit code returned by **e2fsck** is the sum of the following conditions:

- 0 – No errors
- 1 – File system errors corrected
- 2 – File system errors corrected, system should be rebooted
- 4 – File system errors left uncorrected
- 8 – Operational error
- 16 – Usage or syntax error
- 32 – E2fsck canceled by user request
- 128 – Shared library error

SIGNALS

The following signals have the following effect when sent to **e2fsck**.

SIGUSR1

This signal causes **e2fsck** to start displaying a completion bar or emitting progress information. (See discussion of the **-C** option.)

SIGUSR2

This signal causes **e2fsck** to stop displaying a completion bar or emitting progress information.

REPORTING BUGS

Almost any piece of software will have bugs. If you manage to find a filesystem which causes **e2fsck** to crash, or which **e2fsck** is unable to repair, please report it to the author.

Please include as much information as possible in your bug report. Ideally, include a complete transcript of the **e2fsck** run, so I can see exactly what error messages are displayed. (Make sure the messages printed by **e2fsck** are in English; if your system has been configured so that **e2fsck**'s messages have been translated into another language, please set the the `LC_ALL` environment variable to `C` so that the transcript of **e2fsck**'s output will be useful to me.) If you have a writable filesystem where the transcript can be stored, the [script\(1\)](#) program is a handy way to save the output of **e2fsck** to a file.

It is also useful to send the output of [dumpe2fs\(8\)](#). If a specific inode or inodes seems to be giving **e2fsck** trouble, try running the [debugfs\(8\)](#) command and send the output of the [stat\(1u\)](#) command run on the relevant inode(s). If the inode is a directory, the **debugfs dump** command will allow you to extract the contents of the directory inode, which can be sent to me after being first run through [uuencode\(1\)](#). The most useful data you can send to help reproduce the bug is a compressed raw image dump of the filesystem, generated using [e2image\(8\)](#). See the [e2image\(8\)](#) man page for more details.

Always include the full version string which **e2fsck** displays when it is run, so I know which version you are running.

ENVIRONMENT

E2FSCK_CONFIG

Determines the location of the configuration file (see [e2fsck.conf\(5\)](#)).

AUTHOR

This version of **e2fsck** was written by Theodore Ts'o <tytso@mit.edu>.

SEE ALSO

[e2fsck.conf\(5\)](#), [badblocks\(8\)](#), [dumpe2fs\(8\)](#), [debugfs\(8\)](#), [e2image\(8\)](#), [mke2fs\(8\)](#), [tune2fs\(8\)](#)