## **NAME**

\_syscall – invoking a system call without library support (OBSOLETE)

# **SYNOPSIS**

# #include unistd.h>

A \_syscall macro desired system call

## **DESCRIPTION**

The important thing to know about a system call is its prototype. You need to know how many arguments, their types, and the function return type. There are seven macros that make the actual call into the system easier. They have the form:

```
_syscall X (type, name, type1, arg1, type2, arg2, ...)
where

X is 0-6, which are the number of arguments taken by the system call type is the return type of the system call name is the name of the system call typeN is the Nth argument's type

argN is the name of the Nth argument
```

These macros create a function called *name* with the arguments you specify. Once you include the \_syscall() in your source file, you call the system call by *name*.

#### FILES

/usr/include/linux/unistd.h

#### **CONFORMING TO**

The use of these macros is Linux-specific, and deprecated.

## **NOTES**

Starting around kernel 2.6.18, the \_syscall macros were removed from header files supplied to user space. Use syscall(2) instead. (Some architectures, notably ia64, never provided the \_syscall macros; on those architectures, syscall(2) was always required.)

The \_syscall() macros do not produce a prototype. You may have to create one, especially for C++ users.

System calls are not required to return only positive or negative error codes. You need to read the source to be sure how it will return errors. Usually, it is the negative of a standard error code, for example, -EPERM. The \_syscall() macros will return the result r of the system call when r is nonnegative, but will return -1 and set the variable errno to -r when r is negative. For the error codes, see errno(3).

When defining a system call, the argument types *must* be passed by-value or by-pointer (for aggregates like structs).

## **EXAMPLE**

```
error = sysinfo(&s_info);
      printf("code error = %d\n", error);
      printf("Uptime = %lds\nLoad: 1 min %lu / 5 min %lu / 15 min %lu\n"
      "RAM: total %lu / free %lu / shared %lu\n"
      "Memory in buffers = %lu\nSwap: total %lu / free %lu\n"
      "Number of processes = %d\n",
      s_info.uptime, s_info.loads[0],
      s_info.loads[1], s_info.loads[2],
      s_info.totalram, s_info.freeram,
      s_info.sharedram, s_info.bufferram,
      s_info.totalswap, s_info.freeswap,
      s_info.procs);
      exit(EXIT_SUCCESS);
  Sample output
      code error = 0
      uptime = 502034s
      Load: 1 min 13376 / 5 min 5504 / 15 min 1152
      RAM: total 15343616 / free 827392 / shared 8237056
      Memory in buffers = 5066752
      Swap: total 27881472 / free 24698880
      Number of processes = 40
SEE ALSO
```

#### SEE ALSO

intro(2), syscall(2), errno(3)

#### COLOPHON

This page is part of release 4.16 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <a href="https://www.kernel.org/doc/man-pages/">https://www.kernel.org/doc/man-pages/</a>.

Linux 2017-09-15 2