NAME

adjtimex, ntp_adjtime - tune kernel clock

SYNOPSIS

#include <sys/timex.h>
int adjtimex(struct timex *buf);
int ntp adjtime(struct timex *buf);

DESCRIPTION

Linux uses David L. Mills' clock adjustment algorithm (see RFC 5905). The system call **adjtimex**() reads and optionally sets adjustment parameters for this algorithm. It takes a pointer to a *timex* structure, updates kernel parameters from (selected) field values, and returns the same structure updated with the current kernel values. This structure is declared as follows:

```
struct timex {
status flag is set, otherwise
microseconds */
long maxerror; /* Maximum error (microseconds) */
long esterror; /* Estimated error (microseconds) */
long constant; /* PLL (phase-locked loop) time constant */
long precision; /* Clock precision
(microseconds, read-only) */
long tolerance; /* Clock frequency tolerance (read-only);
see NOTES for units */
struct timeval time;
/* Current time (read-only, except for
ADJ_SETOFFSET); upon return, time.tv_usec
contains nanoseconds, if STA_NANO status
flag is set, otherwise microseconds */
long ppsfreq; /* PPS (pulse per second) frequency
(read-only); see NOTES for units */
long jitter; /* PPS jitter (read-only); nanoseconds, if
STA_NANO status flag is set, otherwise
microseconds */
int shift;
             /* PPS interval duration
(seconds, read-only) */
long stabil; /* PPS stability (read-only);
see NOTES for units */
long jitcnt; /* PPS count of jitter limit exceeded
events (read-only) */
long calcnt;  /* PPS count of calibration intervals
(read-only) */
            /* PPS count of calibration errors
long errcnt;
(read-only) */
events (read-only) */
int tai;
             /* TAI offset, as set by previous ADJ_TAI
operation (seconds, read-only,
since Linux 2.6.26) */
/* Further padding bytes to allow for future expansion */
```

};

The *modes* field determines which parameters, if any, to set. (As described later in this page, the constants used for **ntp_adjtime**() are equivalent but differently named.) It is a bit mask containing a bitwise-or combination of zero or more of the following bits:

ADJ_OFFSET

Set time offset from *buf.offset*. Since Linux 2.6.26, the supplied value is clamped to the range (-0.5s, +0.5s). In older kernels, an **EINVAL** error occurs if the supplied value is out of range.

ADJ_FREQUENCY

Set frequency offset from *buf.freq*. Since Linux 2.6.26, the supplied value is clamped to the range (-32768000, +32768000). In older kernels, an **EINVAL** error occurs if the supplied value is out of range.

ADJ_MAXERROR

Set maximum time error from buf.maxerror.

ADJ_ESTERROR

Set estimated time error from buf.esterror.

ADJ_STATUS

Set clock status bits from buf.status. A description of these bits is provided below.

ADJ_TIMECONST

Set PLL time constant from *buf.constant*. If the **STA_NANO** status flag (see below) is clear, the kernel adds 4 to this value.

ADJ SETOFFSET (since Linux 2.6.39)

Add *buf.time* to the current time. If *buf.status* includes the **ADJ_NANO** flag, then *buf.time.tv_usec* is interpreted as a nanosecond value; otherwise it is interpreted as microseconds.

ADJ_MICRO (since Linux 2.6.26)

Select microsecond resolution.

ADJ_NANO (since Linux 2.6.26)

Select nanosecond resolution. Only one of ADJ_MICRO and ADJ_NANO should be specified.

ADJ_TAI (since Linux 2.6.26)

Set TAI (Atomic International Time) offset from buf.constant.

ADJ_TAI should not be used in conjunction with **ADJ_TIMECONST**, since the latter mode also employs the *buf.constant* field.

For a complete explanation of TAI and the difference between TAI and UTC, see .I BIPM

ADJ_TICK

Set tick value from buf.tick.

Alternatively, *modes* can be specified as either of the following (multibit mask) values, in which case other bits should not be specified in *modes*:

ADJ_OFFSET_SINGLESHOT

Old-fashioned **adjtime**(): (gradually) adjust time by value specified in *buf.offset*, which specifies an adjustment in microseconds.

ADJ_OFFSET_SS_READ (functional since Linux 2.6.28)

Return (in *buf.offset*) the remaining amount of time to be adjusted after an earlier **ADJ_OFF-SET_SINGLESHOT** operation. This feature was added in Linux 2.6.24, but did not work correctly until Linux 2.6.28.

Ordinary users are restricted to a value of either 0 or **ADJ_OFFSET_SS_READ** for *modes*. Only the superuser may set any parameters.

The *buf.status* field is a bit mask that is used to set and/or retrieve status bits associated with the NTP implementation. Some bits in the mask are both readable and settable, while others are read-only.

STA PLL (read-write)

Enable phase-locked loop (PLL) updates via ADJ_OFFSET.

STA_PPSFREQ (read-write)

Enable PPS (pulse-per-second) frequency discipline.

STA PPSTIME (read-write)

Enable PPS time discipline.

STA FLL (read-write)

Select frequency-locked loop (FLL) mode.

STA_INS (read-write)

Insert a leap second after the last second of the UTC day, thus extending the last minute of the day by one second. Leap-second insertion will occur each day, so long as this flag remains set.

STA_DEL (read-write)

Delete a leap second at the last second of the UTC day. Leap second deletion will occur each day, so long as this flag remains set.

STA_UNSYNC (read-write)

Clock unsynchronized.

STA_FREQHOLD (read-write)

Hold frequency. Normally adjustments made via **ADJ_OFFSET** result in dampened frequency adjustments also being made. So a single call corrects the current offset, but as offsets in the same direction are made repeatedly, the small frequency adjustments will accumulate to fix the long-term skew.

This flag prevents the small frequency adjustment from being made when correcting for an ADJ OFFSET value.

STA_PPSSIGNAL (read-only)

A valid PPS (pulse-per-second) signal is present.

STA_PPSJITTER (read-only)

PPS signal jitter exceeded.

STA_PPSWANDER (read-only)

PPS signal wander exceeded.

STA_PPSERROR (read-only)

PPS signal calibration error.

STA_CLOCKERR (read-only)

Clock hardware fault.

STA_NANO (read-only; since Linux 2.6.26)

Resolution (0 = microsecond, 1 = nanoseconds). Set via ADJ_NANO, cleared via ADJ_MICRO.

STA_MODE (since Linux 2.6.26)

Mode (0 = Phase Locked Loop, 1 = Frequency Locked Loop).

STA_CLK (read-only; since Linux 2.6.26)

Clock source (0 = A, 1 = B); currently unused.

Attempts to set read-only *status* bits are silently ignored.

ntp_adjtime()

The **ntp_adjtime**() library function (described in the NTP "Kernel Application Program API", KAPI) is a more portable interface for performing the same task as **adjtimex**(). Other than the following points, it is identical to **adjtime**():

* The constants used in *modes* are prefixed with "MOD_" rather than "ADJ_", and have the same suffixes (thus, MOD_OFFSET, MOD_FREQUENCY, and so on), other than the exceptions noted in the following points.

- * MOD_CLKA is the synonym for ADJ_OFFSET_SINGLESHOT.
- * MOD_CLKB is the synonym for ADJ_TICK.
- * The is no synonym for ADJ_OFFSET_SS_READ, which is not described in the KAPI.

RETURN VALUE

On success, adjtimex() and ntp_adjtime() return the clock state; that is, one of the following values:

TIME_OK Clock synchronized, no leap second adjustment pending.

TIME_INS Indicates that a leap second will be added at the end of the UTC day.

TIME_DEL Indicates that a leap second will be deleted at the end of the UTC day.

TIME_OOP Insertion of a leap second is in progress.

TIME_WAIT

A leap-second insertion or deletion has been completed. This value will be returned until the next **ADJ STATUS** operation clears the **STA INS** and **STA DEL** flags.

TIME_ERROR

The system clock is not synchronized to a reliable server. This value is returned when any of the following holds true:

- * Either STA_UNSYNC or STA_CLOCKERR is set.
- * STA_PPSSIGNAL is clear and either STA_PPSFREQ or STA_PPSTIME is set.
- * STA_PPSTIME and STA_PPSJITTER are both set.
- * STA_PPSFREQ is set and either STA_PPSWANDER or STA_PPSJITTER is set.

The symbolic name **TIME_BAD** is a synonym for **TIME_ERROR**, provided for backward compatibility.

Note that starting with Linux 3.4, the call operates asynchronously and the return value usually will not reflect a state change caused by the call itself.

On failure, these calls return -1 and set *errno*.

ERRORS

EFAULT

buf does not point to writable memory.

EINVAL (kernels before Linux 2.6.26)

An attempt was made to set *buf.freq* to a value outside the range (-33554432, +33554432).

EINVAL (kernels before Linux 2.6.26)

An attempt was made to set *buf.offset* to a value outside the permitted range. In kernels before Linux 2.0, the permitted range was (-131072, +131072). From Linux 2.0 onwards, the permitted range was (-512000, +512000).

EINVAL

An attempt was made to set *buf.status* to a value other than those listed above.

EINVAL

An attempt was made to set buf.tick to a value outside the range 900000/HZ to 1100000/HZ, where HZ is the system timer interrupt frequency.

EPERM

buf.modes is neither 0 nor ADJ_OFFSET_SS_READ, and the caller does not have sufficient privilege. Under Linux, the CAP SYS TIME capability is required.

ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

Interface	Attribute	Value
ntp_adjtime()	Thread safety	MT-Safe

CONFORMING TO

Neither of these interfaces is described in POSIX.1

adjtimex() is Linux-specific and should not be used in programs intended to be portable.

The preferred API for the NTP daemon is ntp_adjtime().

NOTES

In struct *timex*, *freq*, *ppsfreq*, and *stabil* are ppm (parts per million) with a 16-bit fractional part, which means that a value of 1 in one of those fields actually means 2^-16 ppm, and 2^16=65536 is 1 ppm. This is the case for both input values (in the case of *freq*) and output values.

The leap-second processing triggered by **STA_INS** and **STA_DEL** is done by the kernel in timer context Thus, it will take one tick into the second for the leap second to be inserted or deleted.

SEE ALSO

settimeofday(2), adjtime(3), ntp_gettime(3), capabilities(7), time(7), adjtimex(8), hwclock(8) NTP Kernel Application Program Interface

COLOPHON

This page is part of release 4.16 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.