#### **NAME**

syslog, klogctl - read and/or clear kernel message ring buffer; set console\_loglevel

### **SYNOPSIS**

```
int syslog(int type, char *bufp, int len);
/* No wrapper provided in glibc */
```

/\* The glibc interface \*/

#include <sys/klog.h>

int klogctl(int type, char \*bufp, int len);

## **DESCRIPTION**

*Note*: Probably, you are looking for the C library function **syslog()**, which talks to **syslog(8)**; see **syslog(3)** for details.

This page describes the kernel **syslog**() system call, which is used to control the kernel *printk*() buffer; the glibc wrapper function for the system call is called **klogctl**().

## The kernel log buffer

The kernel has a cyclic buffer of length **LOG\_BUF\_LEN** in which messages given as arguments to the kernel function **printk**() are stored (regardless of their log level). In early kernels, **LOG\_BUF\_LEN** had the value 4096; from kernel 1.3.54, it was 8192; from kernel 2.1.113, it was 16384; since kernel 2.4.23/2.6, the value is a kernel configuration option (**CONFIG\_LOG\_BUF\_SHIFT**, default value dependent on the architecture). Since Linux 2.6.6, the size can be queried with command type 10 (see below).

#### Commands

The *type* argument determines the action taken by this function. The list below specifies the values for *type*. The symbolic names are defined in the kernel source, but are not exported to user space; you will either need to use the numbers, or define the names yourself.

## SYSLOG\_ACTION\_CLOSE (0)

Close the log. Currently a NOP.

## SYSLOG\_ACTION\_OPEN (1)

Open the log. Currently a NOP.

#### SYSLOG ACTION READ (2)

Read from the log. The call waits until the kernel log buffer is nonempty, and then reads at most *len* bytes into the buffer pointed to by *bufp*. The call returns the number of bytes read. Bytes read from the log disappear from the log buffer: the information can be read only once. This is the function executed by the kernel when a user program reads /proc/kmsg.

### SYSLOG\_ACTION\_READ\_ALL (3)

Read all messages remaining in the ring buffer, placing them in the buffer pointed to by *bufp*. The call reads the last *len* bytes from the log buffer (nondestructively), but will not read more than was written into the buffer since the last "clear ring buffer" command (see command 5 below)). The call returns the number of bytes read.

### SYSLOG ACTION READ CLEAR (4)

Read and clear all messages remaining in the ring buffer. The call does precisely the same as for a *type* of 3, but also executes the "clear ring buffer" command.

### SYSLOG ACTION CLEAR (5)

The call executes just the "clear ring buffer" command. The bufp and len arguments are ignored.

This command does not really clear the ring buffer. Rather, it sets a kernel bookkeeping variable that determines the results returned by commands 3 (SYSLOG\_ACTION\_READ\_ALL) and 4 (SYSLOG\_ACTION\_READ\_CLEAR). This command has no effect on commands 2 (SYSLOG\_ACTION\_READ) and 9 (SYSLOG\_ACTION\_SIZE\_UNREAD).

## SYSLOG\_ACTION\_CONSOLE\_OFF (6)

The command saves the current value of *console\_loglevel* and then sets *console\_loglevel* to *mini-mum\_console\_loglevel*, so that no messages are printed to the console. Before Linux 2.6.32, the command simply sets *console\_loglevel* to *minimum\_console\_loglevel*. See the discussion of */proc/sys/kernel/printk*, below.

The *bufp* and *len* arguments are ignored.

### SYSLOG ACTION CONSOLE ON (7)

If a previous **SYSLOG\_ACTION\_CONSOLE\_OFF** command has been performed, this command restores *console\_loglevel* to the value that was saved by that command. Before Linux 2.6.32, this command simply sets *console\_loglevel* to *default\_console\_loglevel*. See the discussion of */proc/sys/kernel/printk*, below.

The bufp and len arguments are ignored.

## SYSLOG\_ACTION\_CONSOLE\_LEVEL (8)

The call sets *console\_loglevel* to the value given in *len*, which must be an integer between 1 and 8 (inclusive). The kernel silently enforces a minimum value of *minimum\_console\_loglevel* for *len*. See the *log level* section for details. The *bufp* argument is ignored.

## SYSLOG\_ACTION\_SIZE\_UNREAD (9) (since Linux 2.4.10)

The call returns the number of bytes currently available to be read from the kernel log buffer via command 2 (SYSLOG\_ACTION\_READ). The *bufp* and *len* arguments are ignored.

### **SYSLOG ACTION SIZE BUFFER** (10) (since Linux 2.6.6)

This command returns the total size of the kernel log buffer. The *bufp* and *len* arguments are ignored.

All commands except 3 and 10 require privilege. In Linux kernels before 2.6.37, command types 3 and 10 are allowed to unprivileged processes; since Linux 2.6.37, these commands are allowed to unprivileged processes only if <code>/proc/sys/kernel/dmesg\_restrict</code> has the value 0. Before Linux 2.6.37, "privileged" means that the caller has the CAP\_SYS\_ADMIN capability. Since Linux 2.6.37, "privileged" means that the caller has either the CAP\_SYS\_ADMIN capability (now deprecated for this purpose) or the (new) CAP\_SYSLOG capability.

#### /proc/sys/kernel/printk

/proc/sys/kernel/printk is a writable file containing four integer values that influence kernel printk() behavior when printing or logging error messages. The four values are:

### console\_loglevel

Only messages with a log level lower than this value will be printed to the console. The default value for this field is **DEFAULT\_CONSOLE\_LOGLEVEL** (7), but it is set to 4 if the kernel command line contains the word "quiet", 10 if the kernel command line contains the word "debug", and to 15 in case of a kernel fault (the 10 and 15 are just silly, and equivalent to 8). The value of *console\_loglevel* can be set (to a value in the range 1–8) by a **syslog**() call with a *type* of 8.

#### default message loglevel

This value will be used as the log level for *printk()* messages that do not have an explicit level. Up to and including Linux 2.6.38, the hard-coded default value for this field was 4 (**KERN\_WARN-ING**); since Linux 2.6.39, the default value is a defined by the kernel configuration option **CON-FIG\_DEFAULT\_MESSAGE\_LOGLEVEL**, which defaults to 4.

#### minimum\_console\_loglevel

The value in this field is the minimum value to which *console\_loglevel* can be set.

#### default console loglevel

This is the default value for *console\_loglevel*.

## The log level

Every *printk*() message has its own log level. If the log level is not explicitly specified as part of the message, it defaults to *default\_message\_loglevel*. The conventional meaning of the log level is as follows:

Kernel constant	Level value	Meaning
KERN_EMERG	0	System is unusable
KERN_ALERT	1	Action must be taken immediately
KERN_CRIT	2	Critical conditions
KERN_ERR	3	Error conditions
KERN_WARNING	4	Warning conditions
KERN_NOTICE	5	Normal but significant condition
KERN_INFO	6	Informational
KERN_DEBUG	7	Debug-level messages

The kernel *printk()* routine will print a message on the console only if it has a log level less than the value of *console\_loglevel*.

## **RETURN VALUE**

For *type* equal to 2, 3, or 4, a successful call to **syslog**() returns the number of bytes read. For *type* 9, **syslog**() returns the number of bytes currently available to be read on the kernel log buffer. For *type* 10, **syslog**() returns the total size of the kernel log buffer. For other values of *type*, 0 is returned on success.

In case of error, -1 is returned, and *errno* is set to indicate the error.

#### **ERRORS**

## **EINVAL**

Bad arguments (e.g., bad *type*; or for *type* 2, 3, or 4, *buf* is NULL, or *len* is less than zero; or for *type* 8, the *level* is outside the range 1 to 8).

### **ENOSYS**

This **syslog**() system call is not available, because the kernel was compiled with the **CON-FIG\_PRINTK** kernel-configuration option disabled.

#### **EPERM**

An attempt was made to change *console\_loglevel* or clear the kernel message ring buffer by a process without sufficient privilege (more precisely: without the **CAP\_SYS\_ADMIN** or **CAP\_SYSLOG** capability).

## **ERESTARTSYS**

System call was interrupted by a signal; nothing was read. (This can be seen only during a trace.)

## **CONFORMING TO**

This system call is Linux-specific and should not be used in programs intended to be portable.

#### **NOTES**

From the very start, people noted that it is unfortunate that a system call and a library routine of the same name are entirely different animals.

#### **SEE ALSO**

dmesg(1), syslog(3), capabilities(7)

# **COLOPHON**

This page is part of release 4.16 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <a href="https://www.kernel.org/doc/man-pages/">https://www.kernel.org/doc/man-pages/</a>.